

ZagHop Input Manual

Sapunar, M

May 3, 2024

Three files are required for running a trajectory.

1. The main input file containing all of the options for the program.
2. A file containing the initial geometry.
3. A file containing the initial velocity.

The name of the main input file is passed to the program through the command line (if no file name is passed, the default input file is `dynamics.in`). The file is split into sections with options concerning parts of the program. For details on the options, see below. The minimum input is the `$method` section which gives the path to an interface script which communicates between the dynamics and the electronic structure package (see section). In the case of QM/MM dynamics, a second script is used to communicate to the MM package. The QM(MM) driver expects a directory which contains all the input required for a QM(MM) calculation. By default this directory is `"qmdir"("mmdir")`, but can be changed using the `QMDIR(MMDIR)` environment variables.

The geometry file (called `"geom"` by default) contains one line for each atom. Each line contains the atom symbol, atom mass, coordinates and type of atom. The type in the final column is either `"q"` (for QM atoms) or `"m"` (for MM atoms). The velocity file contains just the initial velocity vector for each atom.

A stopped or finished trajectory can be restarted by adding the `$restart` keyword to the input file. In this case, a backup file from a previous trajectory is required instead of the geometry and velocity files.

Program options

method Section `$method` contains paths to the driver programs for running the calculations.
`$method`

<code>qm</code>	No default. Command line call for QM calculation driver.
<code>mm</code>	No default. Command line call for MM calculation driver.
<code>overlap</code>	No default. Command line call for code to calculate the overlap matrix. Run <code>"cis-overlap.exe -h"</code> for command line options.

system Section `$system` contains information about the dimensions of the system and the initial conditions.
`$system`

<code>nstate #</code>	0 Number of states in the QM system.
<code>istate #</code>	nstate Initially populated state. In a FSSH calculation, the initial wave function coefficient of this state will be 1, while others will be 0.
<code>geometry</code>	geom Name of the geometry file, containing the masses and initial positions of the atoms.
<code>velocity</code>	veloc Name of the velocity file, containing the initial velocities of the atoms.
<code>ndim #</code>	3 Number of dimensions per atom.
<code>variable_nstate #</code>	0 Option to change number of states included in calculation on-the-fly. – [0] always use nstate states. – [1] reduce number of states by removing high lying states from the calculation when the absolute value of the corresponding coefficient in the total wave function drops below 0.01. States higher than min_nstate and cstate +1 can be removed.

min_nstate # **0**
 Minimum number of states in the QM system. For **variable_nstate** = 1.
 max_nstate # **0**
 Maximum number of states in the QM system. For **variable_nstate** = 1.

output Section \$output contains options for program output and backup.
 \$output

results_dir **Results**
 Name of the main output file.
 (no)print **1-10**
 Select which output files to print.
 - [1] energy.dat and mm.dat.
 - [2] trajectory.xyz.
 - [3] geometry, atomic units.
 - [4] velocity, atomic units.
 - [5] gradient, atomic units.
 - [6] cwf.dat, wave function coefficients.
 - [7] overlap, overlap matrix for each step.
 - [10] oscill.dat, QM oscillator strengths.
 - [11] qm_traj.xyz, XYZ file containing only QM atoms.
 bufile **backup.dat**
 Name of backup file. The current state is read from this file when restarting the program using the \$restart keyword.
 buinterval # **1**
 The backup file is written every # steps.

dynamics Section \$dynamics contains options for the propagation of the nuclear coordinates.
 \$dynamics

time/max_time # **10.0**
 Total time (in fs) for the propagation of nuclear coordinates.
 timestep # **0.5**
 Time step (in fs) for the propagation of nuclear coordinates.
 orient # **0**
 Select how to handle translation/rotation.
 - [0] do nothing.
 - [1] keep molecule in center of mass.
 - [2] project rotation and translation during dynamics.
 end_state # **0**
 End dynamics after reaching target state.
 end_state_time # **0.0**
 Allow dynamics to run for an additional # fs after reaching target state.
 max_toten_d # **1.0**
 End dynamics if drift in total energy is larger than # eV.
 max_toten_d_step # **0.2**
 End dynamics if change in total energy during a single step is larger than # eV.

constraints Section \$constraints contains constraints to be kept while propagating nuclear coordinates.
 The section contains 1 line defining each constraint. Currently, only bond lengths can be constrained.
 \$constraints

b #1 #2 #3 #4 **No default**
 Freeze bond between atoms #1 and #2 to value #3. If present, #4 is the tolerance for the convergence of the constraint.

surfhop Section \$surfhop contains options for the surface hopping procedure and the propagation of the electronic wave function. If the "\$surfhop off" option is given, the rest of the section is not read and dynamics are performed on the initial adiabatic state without hopping.
\$surfhop (off)

lz	off Instead of the fewest-switches surface hopping algorithm, use Landau-Zener formula to determine hops between surfaces. Most of the other options in the section are ignored.
fssh	adiabatic Use fewest-switches surface hopping algorithm. Possible options: <ul style="list-style-type: none"> – [adiabatic] Propagate electronic wave function coefficients in the adiabatic basis. – [diabatic] Propagate electronic wave function coefficients in the diabatic basis using local diabaticization.
tdse_steps #	10000 Number of substeps for electronic wave function propagation between the nuclear time step at t and at $t + \Delta t$. Energies and couplings are interpolated during the propagation based on the overlap/nadvec and energy options. A hop can occur in any substep of the propagation. Probabilities printed in the main output file are sums of probabilities from each substep.
decoherence	ebd Method used for applying a decoherence correction to the electronic wave function. Possible options: <ul style="list-style-type: none"> – [off] No decoherence correction. – [edc] Energy based decoherence scheme.
overlap	npi Use overlaps between wave functions at the start and end of nuclear time step to calculate time-derivative couplings (TDCs) between states. The TDCs can be interpolated during the propagation between nuclear time steps. Possible options: <ul style="list-style-type: none"> – [constant] Use the finite-differences method to calculate TDCs at $t + \Delta t/2$ and use this value for all substeps. – [linear] Use linear interpolation/extrapolation between the TDCs at $t - \Delta t/2$ and $t + \Delta t/2$. – [npi] Use the norm preserving interpolation method to calculate the average TDCs during the nuclear time step and use this value for all substeps.
phase	2 Method of handling phase of wave functions during dynamics. <ul style="list-style-type: none"> – [0] No phase matching. – [1] Match phase of adiabatic states. – [2] Match phase of diabatic states (using assignment problem solution).
nadvec	linear Use nonadiabatic coupling vectors to calculate time-derivative couplings between states. The TDCs can be interpolated during the propagation between nuclear time steps. Possible options: <ul style="list-style-type: none"> – [constant] Use the TDCs at $t + \Delta t$ for all substeps. – [linear] Use linear interpolation between the TDCs at t and $t + \Delta t$.
energy	linear Method for interpolation of energies during the propagation between nuclear time steps. <ul style="list-style-type: none"> – [constant] Use energies at $t + \Delta t$ for all substeps. – [step] Use energies at t until $t + \Delta t/2$ and energies at $t + \Delta t$ for the second half of the substeps – [linear] Use linear interpolation between energies at t and $t + \Delta t$

velocity	vel Method of rescaling velocity to conserve total energy after a hop. – [off] No rescaling. – [vel] Uniformly rescale velocity. – [gdif] Rescale velocity along vector given by difference of gradients on initial and final surface. – [nadvec] Rescale velocity along nonadiabatic coupling vector.
frustrated	reverse Method of treating frustrated hops (hops rejected due to lack of energy). – [continue] Continue trajectory along previous state. – [reverse] Continue trajectory along previous state, but also invert velocity along the direction along which velocity rescaling was attempted.
lz_prob_conv	0.05 Attempt to predict uncertainty of the estimated LZ probability based on the change in energy when the gap minimum is found and bisect the step until the estimated uncertainty is smaller than the given threshold value. (Set to 1.0 or higher to turn off this behavior.)
lz_min_dt	0.05 Minimum time step (in fs) for the lz_prob_conv procedure.
uncouple_state	none Give list of electronic states which will not be coupled to any others in the surface hopping calculation. When calculating couplings based on overlaps, these states should still be present in the overlap matrix, but all couplings for these states will be set to zero after reading the file. (Example: uncouple_state 1-2, 5).
stop_s0s1_ci	-1.0 Stop the trajectory if it reaches a region close to the S_0/S_1 conical intersection. The trajectory is stopped when $E_1 - E_0 < E_{thr}$ where E_{thr} is given (in eV) by this option. This option is used when potential energies are calculated using single reference methods which give qualitatively wrong results in the S_0/S_1 CI region.
seed #	-1 Give a seed for the random number generator. If seed is < 0 , a seed is generated automatically based on the current time and job ID.

QM interface

The ZagHop dynamics program communicates with electronic structure packages via a file based interface. At every step the program creates three files:

cstep	Containing a single integer for the current step in the dynamics.
qm_state	Containing two integers, the currently populated state (for which the gradient needs to be calculated) and the total number of states.
qm_geom	Containing natom lines with the current geometry of the QM system.

After this, the script given in the "qm" keyword of the \$method section is called. This script should use the information from the files above to run an electronic structure calculation and parse its output to create the following files which will be read by ZagHop and used to propagate the trajectory:

qm_energy	Containing the total energies of all states of the QM system.
qm_grad	Containing natom lines with the gradient of the currently populated state for the current geometry of the QM system.
qm_oscill	If print option 10 is activated, this file should contain the oscillator strengths for the excited states of the QM system.

A python script with drivers for Turbomole and Bagel is included in the package. As an example, dynamics using the Turbomole ADC(2) method would usually have the following line in the dynamics input file:

```
qm "run.py tm_adc2 $QMDIR"
```

where \$QMDIR is an environment variable pointing to a directory where the Turbomole calculation will run (and which contains the required inputs).